



Sinclairville Seed Company LLC

6454 Andrews Rd.
Sinclairville, NY 14782
Phone: (716) 962-8345
Mobile: (716) 499-8720
Sinclairville.Seed@gmail.com

Satisfying the most important clients
"Your Deer and You"

Buck Magnet Planting tips

These recommendations can help you achieve the best results with your food plots.

- Make sure the seed is thoroughly mixed before planting. Some of the small seeds may settle to the bottom during shipping.
1. Buck Magnet should be planted around the 1st of September here in Western New York, earlier further North, and later further South. Best if planted just before a rain (Hint: Have your fields prepared and read to go, and then watch your local weather forecast).
 2. Soil should be fertile with a pH of 6.5 – 7.5. If you are not sure of your soil fertility or pH, have your soil tested. Your local Ag Center or fertilizer dealer can help with this. A good fertilizer recommendation is 300 – 400 lbs/acre of 15-15-15.
 3. Buck Magnet will grow in most soil as long as the soil is well drained and has the proper nutrients and moisture. Approximately one month before planting, condition the soil with a rototiller, disc, chisel plow or similar type of equipment to prepare a good seed bed. Next allow weeds to grow then spray with Roundup 1-2 weeks before planting.
 4. When ready to plant, loosen up seed bed surface by lightly discing or dragging to further prep the soil. Do not till too deep as it will bring more weed seeds to the surface and then they will grow. (This is a good time to spread fertilizer before you loosen up seed bed. It will work fertilizer into soil as you loosen seed bed.)
 5. Using a hand or shoulder seeder, broadcast the seed on top of the soil. Set your seeder on one of the smallest settings. You should see a random oat being planted. Walk fast and crank hard. Better to go back and overlap than run out of seed too soon. If you do this right, you have plenty of seed.
 6. Drilling is also an option but, since the seeds are varying sizes, will be harder to get the correct drill setting. Start with one of the lowest settings on the drill. Do not put the drill in too deep. Seed should be planted no deeper than 3/8". Overlap if needed.
 7. **Important: Use a cultipacker, lawn roller or even your ATV tires to pack the field to insure good seed to soil contact! In planting these seeds it is critical that the seed not be planted any deeper than 3/8".**